

LearnMate LTI

SETUP GUIDE



Catalog # 200081 Rev. A

January 2016

intelitek 

Table of Contents

1.	LTI with LearnMate	1
1.1.	Overview	1
1.2.	The LTI Provider Plugin	1
2.	LTI Provider Setup	2
2.1.	LTI Provider Plugin Settings	2
2.2.	Setting up the Learning Tool for Sharing	3
3.	LTI Consumer Setup	5

Copyright © 2016 Intelitek Inc.

Intelitek Installation User’s Guide

200081 Rev. A

January 2016

Every effort has been made to make this guide complete and as accurate as possible. However, no warranty of suitability, purpose or fitness is made or implied. Intelitek Inc. is not liable or responsible to any person or entity for loss or damage in connection with or stemming from the use of the software, equipment and/or the information contained in this publication.

Intelitek Inc. bears no responsibility for errors which may appear in this publication and retains the right to make changes to the software, equipment and manual without prior notice.

Intelitek Inc.

Toll Free: 800-221-2763

Phone: 603-413-2600

Fax: 603-437-2137

Email: info@intelitek.com

1. LTI with LearnMate

1.1. OVERVIEW

Learning Tools Interoperability (LTI) is a standard whose primary purpose is to connect learning systems such as LearnMate with external service tools. This standard defines the connecting system as an LTI Tool **Consumer** and the connected tool as an LTI Tool **Provider**.

This guide provides instruction for both LTI providers and LTI consumers. Instruction for potential providers begins in the next section. Potential consumers can skip to section 3, LTI Consumer Setup, on page 5.

1.2. THE LTI PROVIDER PLUGIN

The LTI provider plugin comes standard on the LearnMate system. You can use this plugin to share activities and courses with LTI consumers.

The LTI provider plugin has several major features:

- It provides access to full courses or single activities.
- It alters the navigation block of a course or activity for displaying information and links that are related to your current course.
- It enables final grades to be returned to the LTI consumer.
- It allows you to modify the visual features of the course or activity page, such as hiding the header, footer and left or right blocks.
- It provides a single sign on so that users do not have to re-register on the LTI provider platform.

2. LTI Provider Setup


This section describes the steps necessary for sharing content with potential consumers.

2.1. LTI PROVIDER PLUGIN SETTINGS


The LTI provider plugin comes standard with LearnMate 7. However, you can change the settings of the plugin to better suit your own purposes.

To modify the settings of the LTI provider plugin:


1. In the LearnMate 7 administration block, navigate to **Site administration | Plugins | LTI Provider**.



2. Modify settings as desired.



3. Click **Save changes**. The modifications that you made are saved.




2.2. SETTING UP THE LEARNING TOOL FOR SHARING

You can define the learning tool that you want to provide your consumer using the LTI plugin. A learning tool can be an entire course or a single activity within a course.

To define the learning tool:

1. Access the course with the content that you want to share with the consumer.
2. In the administration block, navigate to **Course administration | LTI Provider**.



3. A list of shared learning tools is displayed. The settings of these tools can be edited. Click **Add** to create a new tool.

List of tools provided		
Tool name	Shared secret	Launch URL
Course: mycourse	8ab9cf1cb8e42723403b8e3e1ca46ab3	http://u/satech.i
Course: mycourse	course_secret	http://u/satech.i

Add

4. Define the Tool settings.

The **Tool to be provided** defines what the consumer has access to. It can be the entire course or a single activity.

Tool settings

Tool to be provided Course

Send grades back

Force course or activity navigation

Enrollment duration 0 days Enable

Start date 13 January 2016 Enable

End date 13 January 2016 Enable

- In the Remote system settings, complete the **Shared secret** field. The shared secret is similar to a password. It must be entered by the consumer during setup to obtain access to the tool.

▼ **Remote system**

Shared secret*

Remote system encoding UTF-8 ▼

- Define the remaining settings as desired and then click **Save changes**.

▼ **User default values**

User profile update Always

Email display Allow only other course members to see my email address ▼

City/town*

+ Show more...

▶ **Memberships service settings**

▶ **Layout and CSS**

Save changes
Cancel

The tool is added to the list of tools provided and can be edited later.

List of tools provided		
Tool name	Shared secret	Launch URL
Course: mycourse	8ab9c1f1cb8e42723403b8e3e1ca46ab3	http://localhost:learnmate.com/learnmate/learnmate.php?tool=1
Course: mycourse	course_secret	http://localhost:learnmate.com/learnmate/learnmate.php?tool=2
Course: mycourse	Password1	http://localhost:learnmate.com/learnmate/learnmate.php?tool=3

Add


- i** *Note: The Launch URL displayed in the List of tools provided (above) is used by the consumer to access the learning tool. Ensure that the consumer is provided this URL.*

3. LTI Consumer Setup

LTI consumers can access shared learning tools via LearnMate's **External tool** activity. The external tool enables LearnMate users to interact with LTI-compliant learning resources and activities on other web sites within the LearnMate interface.

To set up an external tool activity in order to access the learning tool of an LTI provider:


1. Enter the course in which you want to add the external tool.
2. In the top-right corner of the page, click **Turn editing on**.



3. In the desired topic or week, click **Add an activity or resource**.



4. In the Add an activity or resource window, select the **External tool** activity.



5. Click **Add** to create the activity.



You are automatically directed to the external tool settings page.

6. In the General settings, complete the **Activity name** field.

▼ **General**

Activity name*	External Course 101
External tool type ?	Automatic, based on launch URL ▼ +
Launch URL ?	
Launch container ?	Default ▼

+ Show more...

7. Click **Show more** to expand the rest of the general settings.




8. Complete the fields of the following settings:


- **Launch URL:** This is the provider tool’s URL. The URL is listed in the provider’s List of tools provided page (See section 2.2 on page 3). This URL should be provided to you, the consumer, by the provider.
- **Consumer key:** This is a username to authenticate access to the tool. It is defined by you, the consumer.
- **Shared secret:** This can be thought of as a password to authenticate the tool. The shared secret is defined by the provider when defining the settings for the tool and should be provided to you, the consumer.

External tool type ?	Automatic, based on launch URL ▾ + ⚙ ✕
Launch URL ?	<input type="text" value="http://intelitek-learnmate.com/external/provider/tool.php?id=3"/> tool configuration.
Secure launch URL *	<input type="text"/>
Launch container ?	Default ▾
Consumer key *	<input type="text" value="Course101"/>
Shared secret *	<input type="text" value="Password1"/> <input checked="" type="checkbox"/> Unmask
Custom parameters *	<input type="text"/>

9. Define the remainder of the settings as desired, and then click **Save and return to course** or **Save and display** to confirm.



The external tool is created and can be accessed by users on the course page.



i *Note: Users do not have to sign on to the provider’s site when accessing the external tool.*